

- Settings : Set warning condition and notify user by send email.

Device Management / Device / 8F44-DAF9-2AEC-86E6-576B-8D20-7926-F209

Statistics Analysis **Setting**

Warning Condition

Total Person: 100 No Mask Threshold: 5 % High Temperature Threshold: 5 % ← 1

At least 100 person and more than 5% of people without masks will trigger warning.
At least 100 person and more than 5% of people with high temperature will trigger warning.

Save

Email Notification 👤 ← 3

Recipient's email: **Add** ← 2

Recipients:

Mail Subject: Please enter mail subject

Mail Content: Please enter mail content

Send Mail

1. Set at least person and the ratio of without mask/high temperature is greater than this threshold will show warning message.
2. Enter recipient's email, mail subject and mail content to send email.
3. Click to set mail server. If the mail server is not certified will show red and can not send email.(Please enter SMTP server)

Mail Server Settings

Server:

Port:

Sender Email:

Sender Password: 🔑

Yes **No**